
Task Manager: "read_file: can't open ../xxx10/pc_display_eng/job-details"

- **Article Type:** General
 - **Product:** Aleph
 - **Product Version:** 20
-

Problem Symptoms:

The GUI Task Manager --> Batch Log --> Batch Job Details gets the following error:

```
read_file: can't open /tmp/utf_files/exlibris/aleph/u21_1/xxx10/pc_display_eng/job-details
```

Cause:

* In xxx50 \$data_root there's a pc_display_eng directory; but in xxx10 \$data_root, there is none.

* ./xxx10/tab/path_convert lacks a line like the following from ./usm10/tab/path_convert:

```
$usm10_dev/usm10/pc_display_eng $usm50_dev/usm50/pc_display_eng
```

Resolution:

1. Add the following line to ./xxx10/tab/path_convert:

```
$xxx10_dev/xxx10/pc_display_eng $xxx50_dev/xxx50/pc_display_eng
```

2. Restart the pc_server.

- **Article last edited:** 12/5/2013