

How to move table to different tablespace

- **Article Type:** General
 - **Product:** Aleph
 - **Product Version:** 21
-

Description:

How would we move a table (znn) to a different tablespace?

Resolution:

You would need to run p_file_03 to back up the table. (Check the \$data_files to make certain that znn.seq has been created.) Then:

change the file_list entry to the desired tablespace;

```
SQL> drop table znn;
```

```
> util a/17/1 znn to create it in the new tablespace. (util a/17/1 can't handle switch of tablespace without the SQL drop.)
```

```
> p_file_04 to load the backed-up table into the new tablespace.
```

Alternatively, the table could be exported/imported using the \$aleph_proc/oracle_expdp_table / \$aleph_proc/oracle_impdp_table procedures. {See KB 16384-56929 ("Use Oracle Data Pump to transfer individual table to Test"). }

- **Article last edited:** 10/8/2013