

util/g/2 counters not being used in patron creation

- **Article Type:** General
 - **Product:** Aleph
 - **Product Version:** 20, 21, 22, 23
-

Problem Symptoms:

When creating a patron in the client the parameters from xxx00 util/g/2 are not being used.

e.g.

6. last-bor-id 646927 n S ABC

xxx00/tab/tab100 has the correct settings:

DEFAULT-BOR-ID=Y

DEFAULT-BOR-ID-1=Y

DEFAULT-BOR-VERIFY-1=N

DEFAULT-BOR-VERIFY-2=N

CHECK-BOR-DEFAULTS=Y

Cause:

ADM library has also counters defined

Resolution:

The system takes the counters last-bor-id, last-bor-id-1, last-bor-verify-1, last-bor-verify-2 in the following order

1. relevant ADM library
2. usr_library

In order to use the counters from the usr_library, remove those from the ADM library.

Important Note: Before you remove any counters, double check, whether the removal will cause any conflicts

- **Article last edited:** 11/20/2013