

What is ue_23? Preventing it from starting automatically

- **Article Type:** General
- **Product:** Aleph
- **Product Version:** 20

Description:

What is ue_23 and how can we prevent it from starting automatically?

Resolution:

ue_23 is related to an interface called "HK System". See "How to Integrate Aleph with HK System" in the Doc Portal - How To - Circulation.

The HK system is an Automated Retrieval System-ARS (also known as Warehouse Management System-WMS) that is used to handle storage and accessibility to library materials that are warehoused at remote storage facilities.

You only need ue-23 when you are using such a system in your library.

v20 rep_change 2595 implements a separate startup_libs environment variable - "HKMESS_STARTUP_LIBS" to handle the ue_23 daemon. As described in the Implementation Notes, you need to comment out the UE_23 lines in your aleph_startup.

If you do not yet have this rep_change, in \$alephe_root/aleph_startup on your server, check if there is the following section:

```
#####  
# UE_23  
#####  
  
echo "starting hk system message daemon..."  
  
if ($?MESSAGE_STARTUP_LIBS) then  
set message_startup_libs = ($MESSAGE_STARTUP_LIBS)  
else  
set message_startup_libs = ""  
endif  
  
foreach lib ($message_startup_libs)  
start_proc00 $lib  
echo " - $active_library "  
source $aleph_proc/util_e_23  
end  
  
echo " "  
  
#####
```

If you change this so that each line is preceded by a hash, then ue_23 will no longer start automatically.

Additional Information

hk system ue_23 ue-23

- **Article last edited:** 10/8/2013