
How to turn PDS off?

- **Article Type:** General
 - **Product:** Aleph
 - **Product Version:** 21
-

Description:

Normally, setting the PDS-AWARE switch from Y to N in the \$alephe_tab/tab100, and restarting the servers should be enough.

We had a customer where this didn't help. The Sign in was still redirected to PDS.

Ori Miller (the 2nd line Aleph Team leader) found that, for this customer, a link to the PDS was added to their HTML page "head-1-nobor" :

```
< <a href="&server_pds?func=load-login&calling_system=aleph&institute=ABC50&url=&pds_backlink?$0100" class="blue" title="Enter your username and password"> Sign-in</a>
```

Ori changed this to:

```
> <a href="&server_f?func=LOGIN-PAGE" class="blue" title="Enter your username and password"> Sign-in</a>
```

and problem has been resolved.

Resolution:

Additional Information

PDS, off

- **Article last edited:** 10/8/2013