

---

## Cannot login to GUI Aleph 19 client

- **Article Type:** General
  - **Product:** Aleph
  - **Product Version:** 19.01
- 

### Description:

I've installed the Aleph 19 GUI client and edited tab and ini files changing USM to ABC.

I am unable to login to Aleph. (I get "Password not verified on connectable hosts".)

### Resolution:

Looking in the \$pw\_library z66 table with util f/4, I find that your ABC log-ins \*are\* present.... The \$LOGDIR/pc\_server log does not show any activity, so it is \*not\* rejecting your log-in; you are not connecting to the pc\_server.

Do your .\ALEPHCOM\TAB\library.ini lines look like this:

```
ABC01 bib ABC01 library.abc.edu:6992
```

They should.

Does each .\xxxx\TAB\per\_lib.ini have "ABCnn" entries? Is the ABCnn first in each per\_lib.ini?

[Later:]

The site had this in their library.ini:

```
ABC01 bib ABC01 IP123.456.543.21:6992
```

when they should have had this:

```
ABC01 bib ABC01 123.456.543.21:6992
```

that is, there should \*not\* be any "IP" preceding the IP address.

---

## Additional Information

faq

---

- **Article last edited:** 10/8/2013