

---

## Self check - Return during loan

- **Article Type:** Q&A
  - **Product:** Aleph
  - **Product Version:** 21
- 

### Question

What should be set in tab100-switch RETURN-DURING-LOAN when return\_during\_loan = Y is set in tab\_sip2.conf?  
Are there other settings that are relevant for this functionality?

### Answer

When in tab\_sip2.conf return\_during\_loan = Y is set, the system is checking tab100-switch RETURN-DURING-LOAN to decide if cash for late return should be generated.

If RETURN-DURING-LOAN = 1 is set no cash will be created, if RETURN-DURING-LOAN = 2 is set a cash may be created. When RETURN-DURING-LOAN = 0 is set no return during loan will be performed.

So tab100-switch RETURN-DURING-LOAN should be set to either 1 or 2 as otherwise return\_during\_loan = Y in tab\_sip2.conf will not have any effect.

---

### Additional Information

tab100-switch RENEW-DURING-LOAN does not influence this functionality.

tab\_sip2.conf-switch circ\_ok should \*NOT\* be set to circ\_ok = Y when you want to use "return during loan". It should be either set to circ\_ok = N or be removed from tab\_sip2.conf (in this case the default circ\_ok = N will be used).

tab\_sip2.conf-switch return\_during\_loan is introduced in Aleph 21 (rep\_ver #017847).

**Category:** Circulation (500)

**Subject:** Self check (500)

---

- **Article last edited:** 10/8/2013