
Base library used in UTIL-G-3, UTIL-G-2, and UTIL-H

- **Article Type:** General
 - **Product:** Aleph
 - **Product Version:** 18.01
-

Description:

UTIL-G-3, UTIL-G-2, and UTIL-H use a "demo library" for getting/comparing values. It seems that different kinds of libraries have different demo libraries. How can we know for a particular library what demo library is being used?

Resolution:

The demo library is determined by two tab100 variables:

(1) BASE-DEMO-LIB: If the value is "2" then the first three characters will be "MAB"; otherwise, the the first three characters will be "USM".

(2) DOC-TYPE-XXX:

If DOC-TYPE-BIB is "Y", then the library number will be "01" (USM01 or MAB01) .

If DOC-TYPE-HOL is "Y", then the library number will be "60" (USM60 or MAB60).

If DOC-TYPE-ADM is "Y", then the library number will be "50" (USM50 or MAB50).

If DOC-TYPE-AUT is "Y", then the library number will be "10" (USM10 or MAB10).

If DOC-TYPE-ILL is "Y", then the library number will be "20" (USM20 or MAB20).

You can see what the base demo library is for a particular library by entering these commands:

```
dlib xxxnn <where "xxxnn" is the library for which you want to do util g/h >
```

```
echo $base_demo_lib
```

[Note: If the base_demo_lib shows as the library itself rather than the USMnn library, see KB 8192-4215.]

Additional Information

faq

- **Article last edited:** 10/8/2013