

How to change the JBoss port in Aleph

- **Product:** Aleph
 - **Product Version:** 20, 21, 22, 23
 - **Relevant for Installation Type:** Dedicated-Direct, Direct, Local, Total Care
-

Description

How to change the JBoss [in v22-up the "Web Services Server"] port in Aleph.

- 1) Shut down JBoss [in v22-up the "Web Services Server"]
 - 2) After backing up the file, update the http.port parameter in \$alephe_root/jboss_conf/global.properties
 - 3) After backing up the file, update the port in the Url template in \$alephe_root/jboss_conf/QuerySyntax.xml
 - 4) Update the Connector port in jdeploy -> jbossweb.sar (sometimes it is jbossweb-tomcat.sar) -> server.xml
 - 5) Copy the file \$alephe_root/jboss_conf/global.properties to the directory \$aleph_dev/ng/aleph/home/profile
 - 6) Navigate to \$aleph_dev/ng/aleph/home/system/bin/ and then run `./set_globals.sh`
 - 7) Start Jboss [in v22-up the "Web Services Server"]
-

- **Article last edited:** 15-May-2016