Changing the 852 1st indicator when running p_manage_50

- **Article Type:** General
- **Product:** Aleph
- **Product Version:** 17.01

Description:
We would like the holding records created with p_manage_50 to have the form:
852 0 b MAIN
rather than
852 b MAIN
How do we achieve this?

Resolution:
You can control the first indicator on the 852 (CALL-NO-TYPE in tab_hol_item_map), but you can't control the second indicator.
However, p-manage-50 does call tab_fix in the XXX60 library (section MNG50). You can use this to call a fix script to change the second indicator. The script routine would be CHANGE-SECOND-IND.

1. In the xxx60/tab/import directory create a fix routine, based on generic_fix, for example fix_852_ind:
! 2 3 4 5 6 7 8 9
!-!!!!!-!!-!-!!!-!!!-!!!!!-!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!-!!!!!!!!!!!!
1 LDR 009 009 CHANGE-SECOND-IND #,1

2. Add this file to tab_fix using the fix_doc_do_file_08 program name in column 2.
The relevant line in $data_tab/tab_fix will appear as follows

! 1 2 3
!!!!!-!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!-!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!>
MNG50 fix_doc_do_file_08 fix_852_ind

- **Article last edited:** 10/8/2013