

## Library Unit

The Library Unit table is a dimension table that stores details about the library in relation to the area that uses it. For example the library unit under the Funds Expenditure SA is the library that manages acquisitions.

Library Unit

Field	Description	Field Location in Alma	Additional Information	Data Type	Data Size
Library Address Line 1	The first line of the address of the institution. It usually includes the building number and the street name.	Configuration > General > Add a Library or Edit Library Information > Contact Information tab. This is taken from the address configured as the <b>Preferred address</b> .  The label in Alma is <code>Address Line 1</code> .		VARCHAR	1000
Library City	The city of the library.	Configuration > General > Add a Library or Edit Library Information > Contact Information tab. This is taken from the address configured as the <b>Preferred address</b> .  The label in Alma is <code>City</code> .		VARCHAR	255
Library Code	The library code	Configuration > General > Libraries > Add a Library or Edit Library Information > Libraries tab > Path [the text after the period]		VARCHAR	50
Library Code (Active)	The code of active (not deleted) libraries	Configuration > General > Libraries > Add a Library or Edit Library Information > Libraries tab > Path [the text after the period]	The same as Library Code without deleted libraries.	VARCHAR	50
Library Country	The country of the library.	Configuration > General > Add a Library or Edit Library Information > Contact Information tab. This is taken from the address configured as the <b>Preferred address</b> .  The label in Alma is <code>Country</code> .		VARCHAR	320
Library Description	The library description	Configuration > General > Libraries > Add a Library or Edit Library Information > Libraries tab  The label in Alma is <code>Description</code> .		VARCHAR	100
Library Name	The library name	Configuration > General > Libraries > Add a Library or Edit Library Information > Libraries tab  The label in Alma is <code>Organization Unit Name</code> .		VARCHAR	255

Field	Description	Field Location in Alma	Additional Information	Data Type	Data Size
Library Name (Active)	The library name of active (not deleted) libraries	Configuration > General > Libraries > Add a Library or Edit Library Information > Libraries tab  The label in Alma is <code>Organization Unit Name</code> .	The same as Library Name without deleted libraries.	VARCHAR	255
Library Postal Code	The postal code of the library.	Configuration > General > Add a Library or Edit Library Information > Contact Information tab. This is taken from the address configured as the <b>Preferred address</b> .  The label in Alma is <code>Postal code</code> .		VARCHAR	200
Library State Province	The state or province of the library.	Configuration > General > Add a Library or Edit Library Information > Contact Information tab. This is taken from the address configured as the <b>Preferred address</b> .  The label in Alma is <code>State/Province</code> .		VARCHAR	320
Unit Type	The type of organization unit	Configuration > General > Libraries > Add a Library or Edit Library Information > Libraries tab  The label in Alma is <code>Organization Unit Type</code> .	Values can be Institution/ Library	VARCHAR	20